

## Release Notes for INSPECTIS CAP Basics Version 6.0 through 6.2.16

### News:

1. An uncalibrated image can be calibrated by software using a known reference distance on the image.
2. Number of displayed decimals for measurements (accuracy) can be set from 1 to 6 (0 to 0.00001) under Preferences. Default is set to 2 decimals (0.01).
3. Grid overlay is moveable across image field. Center of the Grid pattern is highlighted by a circle.
4. Current position of Grid overlay is saved when program closed.
5. Grid overlay can be centered automatically by mouse right-click.
6. Rectangle overlay can be centered automatically by mouse right-click.
7. Current position of Rectangle overlay is saved when program closed.

### Improvements:

1. User interface for "Select Working Folder" is improved.
2. Size and position of the icons on main window is adjusted.
3. License Agreement Updated.

### Bugfixes:

1. Still images did not save under current Working Directory if its name was changed.
2. Calibration issues while changing the resolution causing wrong geometrical measurements.